


## How to Install VisionTRX

1. Hello everyone, this video will explain how to install VisionTRX.
2. The first step is to open the email from ETS-Lindgren with the VisionTRX install instructions.
  - a. Go to the bottom of the email, there will be link to your new VisionTRX version with a download for a zip file.
  - b. Copy the link into your browser and it will immediately download the file.
  - c. This may take a few minutes.
3. Before installing any new versions, first go to the Windows Setting and then Apps, and search for VisionTRX.
  - a. Uninstall the old versions (if applicable) and then restart your computer.
4. Next go to your downloads, and then right-click on the zip file and Extract All.
  - a. The first step is to run the VisionTRX.msi installer by double-clicking on it.
    - i. You may get a warning, click Run Anyway.
    - ii. Click Next and Accept all license agreements as needed.
    - iii. The install may take a few minutes and then click Finish.
    - iv. Once the install is complete go ahead and reboot, this is NOT optional.
  - b. Next go back to your downloads and inside the VisionTRX file, run the HASPUserSetup.exe.
    - i. Click Next and Accept all license agreements.
    - ii. Click the Finish button and then plug-in the VisionTRX HASP key.
    - iii. The key should light up red and wait about five minutes to install all of the HASP drivers that you just installed.
    - iv. Once the five minutes are over, unplug the key again and then reboot your computer, this is NOT optional.

5. Next go to the Control Panel.




- In the top right-hand corner, there is a search bar.
- Search for "Allow" and there should be an option to "Allow an App through Windows Firewall".
- Scroll down until you find vision.trx.exe, and make sure all three settings are checked.
- This will allow VisionTRX to properly communicate with any instruments or cameras that you may have plugged in.
- Click OK and close out the Control Panel.

6. Finally, plug-in your VisionTRX key and then go open VisionTRX.



a. On the toolbar menu go to Help and then License, and you should see your key status as seen here.



The screenshot shows a 'License Information' dialog box with the following fields and values:

- USB Hasp Key ID: 24994919
- Customer SN: (empty)
- Maintenance Expiration: 07/03/2022
- License Status: License Valid (permanent)
- Days to Expiration: 43
- License String: License Level = 3

The License String field contains the following alphanumeric string:

```
eVFAz8sOjGu3rStNXUD13QBLVNX4iWucF5ICNS3Qvgj2ZPu/Kimz3JDU1Cv3r2LC
hZYDRCB+Mp1cT5tL6VA3v4EKB5M+djvmmBZR/BFZd//69Kvb9yt+zG4k5WUyxC2a
T7lmkZaBZVleEqpRW5n0ZPUEB1xY907JepUIY6Htab1nMXkOemkzppqPunPUBSLc
3yBGY7FjmJ0AppgMyp40/+kzRtmuMiJCMmiqiBnziDA1kd7mSLFNGSNbPZHDHoxh
ghUjL1+ZgigFDWEOXoUp5EDuKPB1NJSRjrulbnorxZRBnpWCbrGsuNrl9o9Fdff
x0RkMKoObZ0yLipXfci06V45uL83sjJvQvICY3/5FKQ4n+XB+K3rfrkzm96q9CR
eg+ba2NCQobecOqhMbc8JovcpzPnlh+JbFnzqF91GZzFw08dz9jJDNEqd6XI05n0
z3gCROt/9vjSTO1ceD/4x4tum47fvFjhiurHZNhjalhPgAAMuzAn0JrYpqdW5EgZ
BpzgFDFSURtWKXxFPYKzg1j3afbCWJAP8H4KdQ==
```

At the bottom of the dialog box are five buttons: OK, Refresh, Clear, Update License, and Cancel.

b. If your license is not already setup, please watch the *How to update VisionTRX license String* video, or contact the support group ([TileSupport@ets-lindgren.com](mailto:TileSupport@ets-lindgren.com)) and they can help with the next step.

7. Thank you for watching this video.